

FileTransporter

Instructions for working with the program

Content

Introduction	3
Features	5
What's New?	9
Where to start?	10
System requirements	11
Get help	12

Introduction

The program «**FileTransporter**» designed for file operations (copying and moved) to set selection criteria (file extension) and the execution interval (time repeat surgery).



Exterior and government program


- 1 – the menu bar;
- 2 – numbered folder tasks;
- 3 – the task interval;
- 4 – mode program (copy or move files);
- 5 – mode of rewriting files with the same name;
- 6 – panel "Monitoring and Statistics";
- 7 – select window extension files;
- 8 – button simultaneously stops all tasks performed (if the active task button is not shown);
- 9 – a window to enter comments to the task (separate for each);
- 10 – a mark to start / stop the task (if the task was started, the timer operation of selected tasks will set by the maximum at position 17);
- 11 – marking the creation of subfolders in the destination folder with names and dates of the files;
- 12 – the path to the output folder;
- 13 – the path to your destination;
- 14 – the status of (red – inactive task, green – active task) and the button to move it to the specified number problem;
- 15 – number of the task. When performing file operations, it stands out in green;
- 16 – box files with a spear selected according to the criteria specified under item 7;
- 17 – the next timer operation (in seconds);
- 18 – button to select the source folder;
- 19 – button to select destination folder;
- 20 – button for re-reading the list of selected files;
- 21 – progress bar to copy / move files;
- 22 – the total number of files moved and copied on all tasks;
- 23 – the number of active tasks;
- 24 – the total number of copied files on all tasks;
- 25 – total number of moved files on all tasks;
- 26 – Errors Log.

Features


Key features:

1. To copy or transfer files on the specified selection criteria:

- "**Execution interval**" - an interval of the operation: 1, 10, 30 or 60 minutes.



- "**To select files**" - file extensions, that are necessary for the operation: *. * - all files or files with extensions: *.wav, *.mp3, *.txt, *.ini, *.log, *.avi, *.mov, *.h264.




2. ☒ Overwrite files

When the "**Overwrite Files**" box is checked, files with the same name from the "**Output folder**" will be writable in the "**Destination Folder**".


3. ☒ Create in destination folder subfolders with names - file creation dates

If you have selected "**Create in destination folder subfolders with of names - file creation dates**", in the destination folder will be created folders with names - file creation dates. This file will be recorded in this newly created folder in "**Destination folder**" in the "dd.mm.yyyy" format (where dd. - Day, mm. - Month, yyyy. - Year).

Below is an example of how to perform a file transfer operation from the C:\!Test!\Out\ folder to the C:\!Test!\In\ folder.




4.



In the "**List of selected files**" will be displayed on the selected files "**Source folder**" according to the specified selection criteria.


5.



In the paragraph containing "**Mode files**" can be chosen accordingly:

- **Copy** - copy files
- **Move** - transfer files

6.




This button allows you to update the list of selected files. This function is needed to verify the list of selected files when file operations on a given task are not conducted for a long time.


7. When performing a task by copying/transferring files, the number of the tasks in the "**Monitoring and Statistics**" will be highlighted in green.

Task
1
2
3
4
5
6
Total

8. The «**Error Log**» tab will display any errors that occur during the program.




9. Under "**Settings**" you can:




- **Startup program** - used to run the program after launching the operating system;
- **Minimize program to the system tray** - the program minimizes to the system tray near the clock (bottom right of the screen). This program will continue to run in the background. To return to the standard view of the program, you must click on the program icon;
- **Language** - choose a language for the program. Available in English, Russian and Ukrainian;
- **Clear the number of copied/transferred files** - "reset" copied (moved) files;
- **Reset program settings** - reset settings to the default;
- **Clear errors log** – removing from the “**Error Log**” of all records and clearing the ErrorsLog.txt file;
- **On top of all windows** – program window will always be on top of other programs;
- **Close the program** – exit of the program.

10. In the "**Help**" you can:



- **Visit website** - the browser opens the page and website applications (for each selected interface language - their own page)
- **Manual** - opens this instruction;
- **Check for updates** – this checks the website of the program for a new version. When there is an updated version available, you can go to the website of the program and download the new version;

- **Write a letter to the developer** - opens the mail application. In it's absence, the computer copies the Email address of the developer to clipboard;
- **About** - displays basic information about the program and its registration.

11. 

In the window showing "**Next execution through**", a timer displays the number of seconds until the next operation (separate for each task).

12. In Lite-version, only one task is allowed to perform without limitations in functionality. In the registered version (Full version) is the possibility to perform six tasks simultaneously.

13. In order to prevent damage to the operating system and installed program files, the program prohibited transactions with folders: "C:\, C:\Windows\, C:\Program Files\, C:\Program Files (x86)\. Although these restrictions do not apply to subfolders of these directories. So, while working with these folders, it is necessary to be very careful!

14. Access to some folders is only possible if you start the program as an **Administrator**.

15. All changes to the program settings are automatically saved, and the start to the next program is restored.

This also includes auto marked performance problems.

What's New?

Version 1.0

1. The first release of the program. The program was intended only for personal use.

Version 1.1

1. Added the ability to copy files.
2. Added the possibility to overwrite files with the same name.
3. Added panel monitoring and statistical processes.
4. Added the possibility to stop all tasks simultaneously.
5. Added English and Russian localization.

6. Program acquired the Shareware status. Now, the program is distributed as a demo version with limited functionality that can be activated with a special key to get the full version.

Version 1.12

1. Added an errors log.
2. Corrected errors.

Where to start?

For the first time, a window is displayed in demo mode to one available for the task.

The screenshot shows the FileTransporter (Lite) application window. It has a menu bar with 'Settings' and 'Help'. Below the menu bar is a tab labeled '1'. The main area is divided into two sections. The left section contains configuration options for task #1, including a comment field, checkboxes for 'Run the task!' and 'Overwrite files', file management mode (set to 'copy'), a file selection dropdown (set to '*. *'), a checkbox for 'Create in destination folder subfolders with names - file creation dates', interval performance (set to '1 min'), next execution through (set to 'sec.'), output folder (set to 'C:\'), and destination folder (set to 'C:\'). The right section is titled 'List of selected files' and contains a list of files: 9384.img, AMTAG.BIN, autoexec.bat, bootmgr, BOOTNXT, BOOTSECT.BAK, hiberfil.sys, LAQDG, pagefile.sys, Reserve.img, swapfile.sys, and wifi-debug.xml. Below the list is a 'Re-read output folder' button. At the bottom of the window is a 'Monitoring and statistics' section with an 'Errors log' tab. It contains a table with columns: Task, State task, Copied files, Moved files, and Progress of tasks. The table has 6 rows for tasks 1 through 6, and a 'Total' row. All tasks are currently 'OFF' and have 0 files copied or moved. The total progress is 0.

Task	State task	Copied files	Moved files	Progress of tasks
1	OFF	0	0	
2	OFF	0	0	
3	OFF	0	0	
4	OFF	0	0	
5	OFF	0	0	
6	OFF	0	0	
Total	0	0	0	0

To make the program fully functional, you will need to register.

The procedures for obtaining a license for the program are described in detail on the program's website:

<http://vityksoft.inf.ua/pay.html>

The resulting license file should be placed in the program folder.

In this case, you get the full version with six tabs of tasks that can be performed simultaneously.

After starting the program, a tab with the first task will open by default In the program window.

Select "**Output folder**" - folder where the files will be taken from for operations.

Choose a "**Destination folder**" - folder in which files will be moved to.

Choose File mode: copy – to copy files or move – to move files.

Selected files with which to conduct operations, all files or selected files with specific extensions.

Choosing whether to overwrite files with the "**Source folder**" in the "**Destination folder**" if their names match.

If necessary, select the "**Create in destination folder subfolders with names - file creation dates**".

Select "**Run the task!**" to launch the process for the selected task. After that, all options for file operations of the activated task will be disconnected. Except stop the task. This program appears in the "**STOP**" button in red, which enables you to simultaneously stop all tasks being performed.

Stopping the execution of specific tasks can be selected by clicking the tab with the number of the problem and remove the check mark in "**Run the task!**".

After activation of tasks in the "**Monitoring and statistics**", LED activity for running tasks changes color from red to green.

The column containing "**Copied files**" and "**Moved Files**" shows the number of files copied and transferred respectively for each task.

Also in the "**Monitoring and statistics**" is displayed the number of active tasks and the total number of files copied and transferred to all the objectives.

If errors are detected when working with files, the errors in the "**Error Log**" tab will display the existing errors with the date, time, task number and description of the error. In this case, the "**Error Log**" tab will be automatically activated and the error message will be stored in the ErrorsLog.txt file in the application folder.

Updating the list of selected files is active for tasks every three seconds.

System requirements

System Requirements OS:

- Windows XP (x86) with Service Pack 3 (SP3) - all editions except Starter
- Windows Vista (x86 and x64) with Service Pack 1 (SP1) - all editions except Starter
- Windows 7 (x86 and x64)
- Windows 8 (x86 and x64)
- Windows 8.1 (x86 and x64)
- Windows 10 (x86 and x64)
- Windows Server 2003 (x86 and x64) with Service Pack 2 (SP2)
- Windows Server 2003 R2 (x86 and x64)
- Windows Server 2008 (x86 and x64) with Service Pack 2 (SP2) - Windows Server 2008 R2 (x64)

Hardware Requirements:

CPU with 1.6GHz or higher

1024 MB RAM

1 GB of free disk space

Hard disk speed of 5400 rev / min

Video card with support for DirectX 9 and resolution 1280 x 1024 (or higher)

Microsoft.NET Framework 4.0 or higher.

Get help

For questions about the purchase of a license for the program «**FileTransporter**», to work with the program, bugs and suggestions for improving the program, please contact us by email:

mail@vityksoft.inf.ua

Website of the program: <http://www.vityksoft.inf.ua/>

Program author: Victor Nashylov, Ukraine. 2018 year.