



# FileTransporter

**Version 1.3**

Instructions for working with the program

## Content

Introduction .....	3
Features .....	5
What's New? .....	10
Where to start?.....	11
System requirements .....	13
Get help .....	13

## Introduction

The program «**FileTransporter**» designed for file operations (copying and moved) to set selection criteria (file extension) and the execution interval (time repeat surgery).

### Exterior and government program

The screenshot shows the FileTransporter (Full) application window. The interface includes a menu bar with 'Settings' and 'Help'. Below the menu bar is a toolbar with buttons labeled 1 through 6 and a 'STOP' button (8). The main area is divided into two panes. The left pane contains settings for file management, including a toggle switch (10) labeled 'ON', checkboxes for 'Overwrite files' (11) and 'Create in destination folder subfolders with names - file creation dates' (12), and text boxes for 'Output folder' (13) and 'Destination folder' (13). The right pane displays a 'List of selected files' (16) with a scrollable list of files (17) and a 'Re-read output folder' button (20). At the bottom, there is a 'Monitoring and statistics' section (14) with a table showing task details and progress. The table has columns for Tasks, Mode, Timers, State tasks, Selected files, Copied files, Moved files, and Progress of tasks. The table shows six tasks (1-6) and a total row. Task 2 and 3 are highlighted in green, indicating they are active. Task 1 is highlighted in blue, indicating it is selected. Task 5 and 6 are highlighted in red, indicating they are in a different state. The 'Total' row shows 2 tasks, 18 selected files, 16 copied files, 0 moved files, and 16 progress. The 'Errors log' tab is also visible.

Tasks	Mode	Timers	State tasks	Selected files	Copied files	Moved files	Progress of tasks
1	copy		OFF	0	0	0	
2	copy	00:09:58	ON	2	0	0	
3	copy	00:00:59	ON	16	16	0	
4	copy		OFF	0	0	0	
5	move		OFF	0	0	0	
6	move		OFF	0	0	0	
Total			2	18	16	0	16


- 1 – the menu bar;
- 2 – numbered folder tasks;
- 3 – task start / stop button (if the task has been started, the timer for the operation of the selected task is set to the maximum according to the selected value in position 17);
- 4 – panel "Monitoring and Statistics";
- 5 – Errors Log;
- 6 – mode program (copy or move files);
- 7 – select window extension files;
- 8 – button simultaneously stops all tasks performed (if the active task button is not shown);
- 9 – a window to enter comments to the task (separate for each);
- 10 – mode of rewriting files with the same name;
- 11 – marking the creation of subfolders in the destination folder with names and dates of the files;
- 12 – the path to the output folder;
- 13 – the path to your destination;
- 14 – visual display of the mode of working with files for each task;
- 15 – number of the task. When performing file operations, it stands out in green;
- 16 – box files with a spear selected according to the criteria specified under item 7;
- 17 – the task interval;
- 18 – button to select the source folder;
- 19 – button to select destination folder;
- 20 – button for re-reading the list of selected files;
- 21 – progress bar to copy / move files;
- 22 – the total number of files moved and copied on all tasks;
- 23 – timer to the next operation;
- 24 – indicator status of tasks (gray - the task is not active, green - the task is active), as well as the button for switching to the corresponding task number;
- 25 – the number of active tasks;
- 26 – total number of selected files for all tasks;
- 27 – the total number of copied files on all tasks;
- 28 – total number of moved files on all tasks.

## Features


Key features:

1. To copy or transfer files on the specified selection criteria:

- **"Execution interval"** - an interval of the operation: 1 minute, 10 minutes, 30 minutes, 60 minutes (1 hour) or 180 minutes (3 hours).



- **"To select files"** - file extensions, that are necessary for the operation: \*.\* - all files or files with extensions: \*.wav, \*.mp3, \*.txt, \*.ini, \*.log, \*.avi, \*.mov, \*.h264.





2. ☒ Overwrite files


When the **"Overwrite Files"** box is checked, files with the same name from the **"Output folder"** will be writable in the **"Destination Folder"**.

3. ☒ Create in destination folder subfolders with names - file creation dates

If you have selected **"Create in destination folder subfolders with of names - file creation dates"**, in the destination folder will be created folders with names - file creation dates. This file will be recorded in this newly created folder in **"Destination folder"** in the "dd.mm.yyyy" format (where dd. - Day, mm. - Month, yyyy. - Year) that are below the given example.




In the "**List of selected files**" will be displayed on the selected files "**Source folder**" according to the specified selection criteria.



In the paragraph containing "**Mode files**" can be chosen accordingly:

- **Copy** - copy files
- **Move** - transfer files




This button allows you to update the list of selected files. This function is needed to verify the list of selected files when file operations on a given task are not conducted for a long time.


7. When performing a task by copying/transferring files, the number of the tasks in the "**Monitoring and Statistics**" will be highlighted in green.

Tasks
1
2
3
4
5
6

8. The «**Error Log**» tab will display any errors that occur during the program. The last error will be highlighted in blue.




9. Under "**Settings**" you can:



- **Startup program** - used to run the program after launching the operating system;
- **Minimize program to the system tray** - the program minimizes to the system tray near the clock (bottom right of the screen). This program will continue to run in the background. To return to the standard view of the program, you must click on the program icon;
- **Language** - choose a language for the program. Available in English, Russian and Ukrainian;
- **Clear the number of copied/transferred files** - "reset" copied (moved) files;
- **Reset program settings** - reset settings to the default;
- **Clear errors log** – removing from the “**Error Log**” of all records and clearing the ErrorsLog.txt file;
- **On top of all windows** – program window will always be on top of other programs;
- **Close the program** – exit of the program.

10. In the "**Help**" you can:



- **Visit website** - the browser opens the page and website applications (for each selected interface language - their own page)
- **Manual** - opens this instruction;
- **Check for updates** – this checks the website of the program for a new version. When there is an updated version available, you can go to the website of the program and download the new version;
- **Write a letter to the developer** - opens the mail application. In it's absence, the computer copies the Email address of the developer to clipboard;
- **About** - displays basic information about the program and its registration.

11.

Timers
00:09:09
00:00:23



The "**Timers**" column in the "**Monitoring and Statistics**" panel displays timers for the next execution of the operation (individually for each task) in the format: **xx:yy:zz**, where **xx** - hours, **yy** - minutes, **zz** - seconds.

12.

Mode
copy
copy
copy
copy
move
move

The "**Mode**" column in the "**Monitoring and Statistics**" panel displays file modes (copy or move).

13.

State tasks
OFF
ON
ON
OFF
OFF
OFF

The "**State tasks**" column in the "**Monitoring and Statistics**" panel displays task states (**OFF** on a gray background - the task is not active, **ON** on the green background - the task is active).

14. In Lite-version, only one task is allowed to perform without limitations in functionality. In the registered version (Full version) is the possibility to perform six tasks simultaneously.

15. In order to prevent damage to the operating system and installed program files, the program prohibited transactions with folders: "C:\, C:\Windows\, C:\Program Files\, C:\Program Files (x86)\. Although these restrictions do not apply to subfolders of these directories. So, while working with these folders, it is necessary to be very careful!

16. Access to some folders is only possible if you start the program as an **Administrator**.

17. All changes to the program settings are automatically saved, and the start to the next program is restored. This also includes auto marked performance problems.

## What's New?

### Version 1.0

1. The first release of the program. The program was intended only for personal use.

### Version 1.1

1. Added the ability to copy files.
2. Added the possibility to overwrite files with the same name.
3. Added panel monitoring and statistical processes.
4. Added the possibility to stop all tasks simultaneously.
5. Added English and Russian localization.
6. Program acquired the Shareware status. Now, the program is distributed as a demo version with limited functionality that can be activated with a special key to get the full version.

### Version 1.2

1. Added an errors log.
2. Corrected errors.

### Version 1.3

1. The paths to the input and output folders can now be set directly in the path line.
2. In the monitoring and statistics window, a visual indication of the modes of working with files and timers for each task separately is added.
3. The program interface is redone.
4. Bug fixes fixed.
5. Program code is optimized.

## Where to start?

For the first time, a window is displayed in demo mode to one available for the task and English interface.

Tasks	Mode	Timers	State tasks	Selected files	Copied files	Moved files	Progress of tasks
1	copy		OFF	0	0	0	
2	copy		OFF	5	0	0	
3	copy		OFF	0	0	0	
4	copy		OFF	0	0	0	
5	copy		OFF	0	0	0	
6	copy		OFF	0	0	0	
Total			0	5	0	0	0

To make the program fully functional, you will need to register.

The procedures for obtaining a license for the program are described in detail on the program's website:

<http://vityksoft.inf.ua/>

The resulting license file should be placed in the program folder.

In this case, you get the full version with six tabs of tasks that can be performed simultaneously.

After starting the program, a tab with the first task will open by default in the program window.

Select "**Output folder**" - folder where the files will be taken from for operations.

Choose a "**Destination folder**" - folder in which files will be moved to.

Choose the mode of working with files: copy - copy or move - move.

Selected files with which to conduct operations, all files or selected files with specific extensions.

Choose an interval, after which time the task will be repeated.

Choosing whether to overwrite files with the "**Source folder**" in the "**Destination folder**" if their names match.

If necessary, select the "**Create in destination folder subfolders with names - file creation dates**".

Click the button



to start the process on the selected task. After that, all options for operations with files of the activated task will be disabled. Except for stopping the task. At the same time in the window of the program there is a button "**Stop**" of red color, with which you can simultaneously stop all tasks that are performed.

To stop the execution of a specific task you can go to the tab with the task number and click on the button



After activation of tasks in the "**Monitoring and statistics**", LED activity for running tasks changes color from red to green.

The column containing "**Copied files**" and "**Moved Files**" shows the number of files copied and transferred respectively for each task.

Also, in the "**Monitoring and statistics**" is displayed the number of active tasks and the total number of files copied and transferred to all the objectives.

If errors are detected when working with files, the errors in the "**Error Log**" tab will display the existing errors with the date, time, task number and description of the error. In this case, the "**Error Log**" tab will be automatically activated and the error message will be stored in the **ErrorsLog.txt** file in the application folder.

Updating the list of selected files is active for tasks every three seconds.

## System requirements

System Requirements OS:

- Windows XP (x86) with Service Pack 3 (SP3) - all editions except Starter
- Windows Vista (x86 and x64) with Service Pack 1 (SP1) - all editions except Starter
- Windows 7 (x86 and x64)
- Windows 8 (x86 and x64)
- Windows 8.1 (x86 and x64)
- Windows 10 (x86 and x64)
- Windows Server 2003 (x86 and x64) with Service Pack 2 (SP2)
- Windows Server 2003 R2 (x86 and x64)
- Windows Server 2008 (x86 and x64) with Service Pack 2 (SP2) - Windows Server 2008 R2 (x64)

Hardware Requirements:

CPU with 1.6GHz or higher

1024 MB RAM

1 GB of free disk space

Hard disk speed of 5400 rev / min

Video card with support for DirectX 9 and resolution 1280 x 1024 (or higher)

Microsoft.NET Framework 4.0 or higher.

## Get help

For questions about the purchase of a license for the program «**FileTransporter**», to work with the program, bugs and suggestions for improving the program, please contact us by email:

[mail@vityksoft.inf.ua](mailto:mail@vityksoft.inf.ua)

Website of the program: <http://www.vityksoft.inf.ua/>

Program author: Victor Nashylov, Ukraine. 2019 year.